## Manual HC-IQ detect

Run HIQ Configurator and in "System" page check for which HC-IQ is configured.



15789

Find your HC-IQ serial number (sticker on top of HC-IQ - 15789 in following example).

Find and open in your preferred text editor "*CyBroMiniScada.xml*" HIQ Configurator configuration file. It is usually in "C:\Program Files (x86)\HIQ Configurator\" folder.

**Replace all** occurrences of c[old\_S/N] with c[new\_S/N] (c1000 with c15789 for our example).

The Life Assessed View Viela	
-crafte	
the proval servings on	
ATTACK OF AN ALL AND A COMPANY	
<pre>chapaticsbapaticsbapatics</pre>	Name of the Address o
21222323237272	2 3 1000.0
the pape surgerine co-	Charlos P Linkski
And Andrewson an	
c)- sight definitions	
Hard State And State and State And	
All the section of th	



........

HIO

000000

HC-10

Last update: 2018/10/05 en:hiq\_home:applications:configurator:manual\_detect http://wiki.hiq-home.com/doku.php?id=en:hiq\_home:applications:configurator:manual\_detect 13:06

From: http://wiki.hiq-home.com/ -

Permanent link: http://wiki.hiq-home.com/doku.php?id=en:hiq\_home:applications:configurator:manual\_detect

Last update: 2018/10/05 13:06

